

What's New

The BR86 Comments field has joined the BR86 form, which should eliminate any errors you may have encountered in the past.

MAIN BRIDGE INSPECTION - BR86

COMMCENTER : [BR86 MANUAL](#) TODAY'S DATE: 4/20/2009
[BR87 MANUAL](#) CURRENT TIME: 1:24:50 PM

2030284

1 STRUCTURE FILE NUMBER 7 BRIDGE NUMBER TWP ROUTE UNIT YEAR BUILT
HIC C0109 01.08 0101

DIST 1 BRIDGE TYPE 321 TYPE SERVICE 15 ? or F1 for Context Sensitive Help

CULVERTS CHANNEL APPROACHES GENERAL SUSPENSION BRIDGES MOVABLE BRIDGES COMMENTS

PRINTING BR86 COMMENTS BR86 COMMENTS PRINT SUPPLEMENTAL BRIDGE INSP. REPORT

Preview Current Record

Preview All Records

INSPECTED BY: MLL PE PE REVIEWED BY: WJS PE PE SURVEY: 01111111

INSP. DATE: 121407 REVIEW DATE: 121407

PE INSP. ID: 071261 PE REV. ID: 067103

Record: 1 of 230 No Filter Search

Field or Code Updates:

BR87 Form - Item #164 – Suspension/Cable Stayed has been removed and is now a blank field

A new MPO code item has been added – 17 – Erie Regional Planning Commission (included for the 17 code addition is Erie and Lorain Counties)

BR87 Form – Card C - Item #'s 41 and 42 has a format change:

Item #41 - Date Built (MM/DD/YYYY)


Item #42 - Date of Major Rehabilitation (MM/DD/YYYY)

Note – If you do not fill in the Review By field and Review Date field in the BR86, you will get an error in the error checking.

BR86/87 EXPORT

Some new features are available on the Export BR86/87 form. As every user should know, when exporting the BR87, it only exports those records that got updated since the last export was performed to go to ODOT. No matter what happens to the exported file, (the exported BR87ODOT.TXT file gets lost, or the user accidentally performs the export twice), the records in the BR87 table that get tagged for export still cleared of those flags. The reason they get cleared after the export happens, is so the next time the export occurs, only those records that need exporting, are exported, and does not include the ones that got exported the previous time. Those flags appear when a change is made to the BR87 data in the field that is called the TRAN_CODE field, which resides in the BR87 table.

The BR87 Re-Exporter is a feature that allows the user to re-flag the TRAN_CODE field for individual records. This feature was available in the previous version of the program:



Just click the Help button on the BR87 RE-EXPORTER form for how this works. The new features are the Global Fill-In and Clear buttons. As they suggest, they fill-in and clear the TRAN_CODE field, thus allowing the user to re-export all the BR87 data. Just click the GLOBAL TRAN_CODE FILL-IN, and then click the EXPORT button for the BR87. If for any reason you wish to clear the TRAN_CODE field, you can click the GLOBAL TRAN_CODE CLEAR button to clear the flags from the BR87 table.